

# MPX-OS User Manual

B. Burwell and A. Morash

Fall 2013













actions. Thus, for the most part, the normal behavior of a command is to see no output. For example, when changing the prompt (see p. 9), there is no “prompt changed” message; the user should be able to trust the system to perform correctly.

Thus, messages will generally only be displayed when some unexpected behavior has occurred. For full and more precise details on exactly what the output of each command, see the appropriate documentation in this Manual.











### 3.4.3 Example

1. User calls stop, but does not want to exit:  
**Input:** stop  
**Output:** Are you sure you want to exit? [y/n]:  
**Input:** n  
**Output:** None.
  
2. User calls stop, and does confirm wanting to exit:  
**Input:** stop  
**Output:** Are you sure you want to exit? [y/n]:  
**Input:** y  
**Output:** \*\* COMHAN execution complete \*\*

### 3.4.4 Possible Errors

There are no error conditions.

## 3.5 help

The help command allows the user to get help about using MPX commands. If the command is run with no options, a brief description of all commands. Alternately, if called with the name of a command as an option, it will give only the description of that command.

### 3.5.1 Syntax

The command has the form `help [command]`.

### 3.5.2 Usage

The command can be called at any time through the MPX prompt.

### 3.5.3 Example

1. User wants help for all processes:  
**Input:** help  
**Output:**























